


## Edit-R synthetic guide RNA transfection protocol for Cas9 expressing cells

The following is an abbreviated protocol for transfecting synthetic guide RNA into cultured mammalian cells expressing Cas9 using DharmaFECT™ 1-4 transfection reagent (Cat. T-2001, T-2002, T-2003, T-2004). Synthetic guide RNA can be either synthetic single guide RNA, or synthetic crRNA complexed with tracrRNA. Intended for use after optimization for your cell line has been completed. For full details, as well as optimization guidelines please see the Technical Manual.

This protocol is written for transfection of cells into 96,24, or 6-well tissue culture plates at 25 nM final concentration of synthetic guide RNAs.



96-well protocol				
Day 1				
Cell plating	Seed cells at a density that is optimal for specific downstream phenotypic assay(s)			
Day 2				
Prepare working solutions of reagents for transfection	Synthetic guide RNA	Dilute sgRNA to a working concentration of 2 μM in 10 mM Tris-HCl, pH 7.4 or Dilute and mix crRNA and tracrRNA to a working concentration of 2 μM in 10 mM Tris-HCl, pH 7.4		
Combine		For one well	For multiple wells	
working solutions for	Tube 1			
transfection	Synthetic guide RNA	1.25 µL	_ μL	
mixture	Serum-free medium	To 10 μL	_ µL	
Davis	Tube			
Prepare working solution of Dharmafect 1-4 for transfection	DharmaFECT 1-4	0.05-0.8 μL		
	Serum-free medium	To 10 μL	_ µL	
	Incubate at room temperature for 5 minutes before next step			
	Combine Tube 1 and Tube 2 and carefully mix by pipeting			
Combine transfection mixture	Incubate at room temperature for 20 minutes before next step			
	Add full growth medium	80 μL	_ µL	
	Total	100 μL	_ µL	
Transfect cells	Replace growth medium on cells with 100 μL of transfection mixture			
	Incubate cells for 72-96 hours before performing downstream phenotypic assay(s) or gene editing analysis			

24-well protocol				6-well protocol	
Day 1				Day 1	
Cell plating	Seed cells at a density that is optimal for specific downstream phenotypic assay(s)			Cell plating	Seed cells at downstream
Day 2				Day 2	
Prepare working solutions of reagents for transfection	Synthetic guide RNA		of 2 µM in 1, pH 7.4 orRNA and tracrRNA to entration of 2 µM in	Prepare working solutions of reagents for transfection	Synthetic guide RNA
Combine		For one well	For multiple wells	Combine	
working	Tube 1	Tube 1			Tube 1
solutions for transfection mixture	Synthetic guide RNA	6.25 uL	_ μL	solutions for transfection	Synthetic g
	Serum-free medium	To 50 μL	_ µL	mixture	Serum-free
	Tube 2	Tube 2			Tube 2
Prepare working solution of Dharmafect 1-4 for transfection	DharmaFECT 1-4	0.24-4 uL	_ μL	Prepare working solution of	DharmaFE(
	Serum-free medium	To 50 μL	_ µL	Dharmafect 1-4	Serum-free
	Incubate at room temperature for 5 minutes before next step			for transfection	Incubate a
	Combine Tube 1 and Tube 2 and carefully mix by pipeting				Combine To
Combine transfection mixture	Incubate at room tem	Incubate at room temperature for 20 minutes before next step			Incubate a
	Add full growth medium	400 μL	_ µL	Combine transfection mixture	Add full gro medium
	Total	500 μL	_ µL		Total
Transfect cells	Replace growth medium on cells with 500 uL of transfection mixture		Transfect cells	Replace gr	
	Incubate cells for 72-96 hours before performing downstream phenotypic assay(s) or gene editing analysis			Incubate ce assay(s) or	

6-well protocol					
Day 1					
Cell plating	Seed cells at a density that is optimal for specific downstream phenotypic assay(s)				
Day 2					
Prepare working solutions of reagents for transfection	Synthetic guide RNA	Dilute sgRNA to a working concentration of 2 $\mu$ M in 10 mM Tris-HCl, pH 7.4 or Dilute and mix crRNA and tracrRNA to a working concentration of 2 $\mu$ M in 10 mM Tris-HCl, pH7.4			
Combine		For one well	For multiple wells		
working solutions for	Tube 1				
transfection	Synthetic guide RNA	25 uL	_ μL		
mixture	Serum-free medium	To 200 μL	_ µL		
	Tube 2				
Prepare working solution of Dharmafect 1-4 for transfection	DharmaFECT 1-4	1-20 uL	_ µL		
	Serum-free medium	To 250 μL	_ µL		
	Incubate at room temperature for 5 minutes before next step				
	Combine Tube 1 and Tube 2 and carefully mix by pipeting				
Combine transfection mixture	Incubate at room tem	perature for 20 mir	nutes before next step		
	Add full growth medium	1600 µL	_ µL		
	Total	2000 μL	_ µL		
Transfect cells	Replace growth medium on cells with 2000 uL of transfection mixture				
	Incubate cells for 72-96 hours before performing downstream phenotypic assay(s) or gene editing analysis				

## For more information

To find the contact information in your country for your technology of interest, please visit us at **horizondiscovery.com/contact-us** 

